## Target and shadow databases

ReadyRoll maintains two databases:

• Target database

This is the development database or sandbox that you use for debugging and to edit schema objects (e.g. using SSMS). When you deploy, ReadyRoll executes your migration scripts against this database to upgrade it. You shouldn't drop the target database from your SQL Server instance.

• Shadow database

This is an exact copy of your database schema created automatically from your project scripts (001.sql, 002.sql, 003.sql, etc). It's created every time you use the ReadyRoll tool-window to view pending changes or import. The shadow database is used by the SQL Compare engine (that powers ReadyRoll) as the base from which to generate a new migration script. It is safe to remove the database from your development instance at any time, in fact ReadyRoll will automatically drop the shadow db whenever you Clean or Rebuild your project. *For details of how the shadow databases is used during the verification stage, see script verification.* 

## Changing the Target database connection

The Target Connection string can be set by clicking the Edit button within the Debug tab of the project designer.

Database1 👳 🗙	
Project Settings	Configuration: N/A
SQLCLR	
SQLCLR Build	Target Connection String
Build	Data Source=myinstance.database.windows.net;Initial
SQLCMD Variables	Catalog=Database1;Persist Security Info=False;User ID=myuser;Pooling=False;MultipleActiveResultSets=False;Connect
Build Events	Timeout=60;Encrypt=False;TrustServerCertificate=True
Debug	
Reference Paths	Edit Set As Default Restore Default
Code Analysis	

This will display the connection dialog, from which you can either browse to the desired server or enter the connection details:

🐼 Connect			$\times$
History Browse			
<ul> <li>Favorites</li> </ul>			$\sim$
<pre><default> (local)\SQL14</default></pre>	QUOKKATOWN\daner)	×	
<pre><default>   (local)\SQL201</default></pre>	6 (QUOKKATOWN\daner)	¢	
A Recent Connections			
Database1			$\sim$
✓ Hide Connection Pro	perties		
Server Name:	(local)\SQL14		]
Authentication:	Windows Authentication	Ŷ	
User Name:	QUOKKATOWN\daner		
Password:			
	Remember Password		
Database Name:	Database1	Ŷ	
		Details	
Test Connection	ОК	Cancel	


Build your solution to update the connection within the ReadyRoll tool-window.

ReadyRoll DBSyn	c				<b>-</b> □ ×
🕜 readyroll	Project: Database1	Import and generate script	C Refresh	Help 🔻	redgate
		View Database1			
		Preview objects pending Import			
		CAL)\SQL14].[Database1] <u>Configure</u> CAL)\SQL14].[Database1_daner_SHADOW]			
	Learn more about target				

## Changing the Shadow database connection

By default, the Shadow database will be deployed to the same server that you've chosen to deploy the Target database to.

If you would prefer not to deploy the Shadow database to your Target server, you check the following option on the Debug tab: Always use default connection string for Shadow database.



## Setting the Shadow connection string

To deploy the Shadow to a different server, this can be done by adjusting the default connection string in the project.

Firstly, under the *Target Connection String*, click **Edit** to display the connection dialog. Specify the server that you would like to deploy the Shadow database to:

🔇 Connect		×
History Browse		
<pre>{default&gt;   (localdb)\My</pre>	ShadowServer (QUOKKATOWN\daner)	+
Database1 myinstance.c	database.windows.net (myuser)	
(localdb)\Pro	ojectsV13 (QUOKKATOWN\daner)	~
<ul> <li>Hide Connection Properties</li> </ul>		
Server Name:	(localdb)\MyShadowServer	
Authentication:	Windows Authentication	~
User Name:	QUOKKATOWN\daner	
Password:		
	Remember Password	
Database Name:	<default></default>	¥
		Details
Test Connection	ОК	Cancel

Then, click Set As Default to set this connection as the Default Connection String.

Target Connection String	
Data Source= <mark>(localdb)\MyShadowServer</mark> Initial Catalog=Database1;Integrated Security=True;Persist Security Info=False;Pooling=False;MultipleActiveResultSets=False;Connect Timeout=60;Encrypt=False;TrustServerCertificate=True	
Edit Set As Default Restore Default Default Connection String	
Data Source=(localdb)\MyShadowServer;Initial Catalog=Database1;Integrated Security=True;Persist Security	
Clear	

The Default Connection String is a setting that is included in your .sqlproj file. This means that this setting will be shared with others when you check the project into source control, so the connection details you provide should be valid for everyone in your team.

Click Edit... once again in order to set the Target Connection String back to its previous setting:

0

🔇 Connect		×	<
History Browse			
Favorites		^	
<default> (local)\SQL14</default>	(QUOKKATOWN\daner)	×	
<pre><default> (local)\SQL20*</default></pre>	6 (QUOKKATOWN\daner)	*	
Recent Connections			
Database1		~	
✓ Hide Connection Pro	perties		
Server Name:	(local)\SQL14		
Authentication:	Windows Authentication	Ŷ	
User Name:	QUOKKATOWN\daner		
Password:			
	Remember Password		
Database Name:	Database1	v	
		Details	
Test Connection	ОК	Cancel	

Ensure that the following option is checked: Always use default connection string for Shadow database.

Build the solution to update the connection details within the ReadyRoll tool-window. ReadyRoll DBSync

ReadyRoll DBSyn	c			<b>-</b> □ ×
🜈 readyroll	Project: Database1	Import and generate script	CRefresh Help 🔻	redgate
		View Database1 Preview objects pending Import CALD\SQL14].[Database1] Configure CALDB\\MYSHADOWSERVER].[Database1_daner_SHAI and shadow databases	DOW]	

When you next Import changes into your project, the Shadow database will be deployed to the specified server. Feel free to drop any databases ( created by ReadyRoll on any of your other servers (this can be identified by the \_SHADOW database name suffix).